

---

## AVImark Software Support

**Address:** 5 Sugar Creek Road Piedmont, MO 63957

**Support Phone:** 877.838.9273 | **Support Fax:** 573.223.4306

**Corporate Phone:** 855.838.7638 | **Corporate Fax:** 573.223.3551

# Installing the Dymo Label Writer Twin Turbo to work with AVImark

## **Installing the Dymo Label Writer Twin Turbo to work with AVImark**

The Dymo Label Writer Twin Turbo can be installed twice, on the same computer, each with a different name, and then the form assignment set for the left and right rolls separately. Example: The Label Writer is installed on the same computer twice as Dymo 30258 and Dymo 30252. This allows for the AVImark program to see two separate label printers and a form assignment can be chosen for each one.

Please have your Computer Technician follow these instructions:

1. Install the Dymo Label Writer Twin Turbo on your computer using the manufacturer's software and following the manufacturer's instructions. Do not connect your printer to the computer until prompted by the Dymo software.
2. Go into the Printer Properties, Advanced, Printing Defaults, Paper/Quality tab and set the primary roll as the left roll. Click apply.
3. Still in printer properties, select the Layout tab and choose Landscape. Click the Advanced button, at the bottom of the screen, and select the correct paper size.
4. Click on the General Tab, Printing Preferences and repeat steps 2 and 3. Click OK and close the Properties window.

Reinstall the Dymo Label Writer Twin Turbo on the computer second time following these steps:

1. In your Printers folder double click on Add a Printer.
2. Choose Local Printer (in XP uncheck the detect printer option)
3. Select use an existing port and choose the USB port then click next.
4. Select Dymo, from the Manufacturers box, then choose the Dymo Twin Turbo
5. Use the driver that is already installed and click next.
6. Do not select the option to set as the default printer.

7. Go into the Printer Properties, Advanced, Printing Defaults, Advanced tab and set
8. The primary roll as the right roll then click apply.
9. Still in printer properties, select the Layout tab and select Landscape. Click the Advanced button, at the bottom of the screen, and select the correct paper size.
10. Open AVImark and go to Utilities, Printer Setup and select the correct printer for the appropriate task.
11. Still in the Printer Setup window select the Form Assignment tab setting the form assignment for each Dymo Label Writer Twin Turbo. Click Done